



ZIPMONEY  
SETUP GUIDE FOR

**eCorner** Stores

**CONTENTS**

1. Add ZipMoney payment method to your online shop.....	2
2. Configure and activate ZipMoney payment method .....	3
3. Setup zipMoney marketing and display features .....	4
3.1 Add zipMoney widget(s) to product and cart pages .....	4
3.2 Add zipMoney landing page to your website menus .....	6
3.3 Add zipMoney icon to footer section .....	7
3.4 Add zipMoney logo to your website .....	7

1. ADD ZIPMONEY PAYMENT METHOD TO YOUR ONLINE SHOP

1. Go to the **Settings menu >> Payment**
2. Select **zipMoney** on the dropdown list and click the **Save** button, this will add a new zipMoney payment method to your shop.

Settings for payment

Payment methods | Dependencies | Deferred payment | Credit check and collection services

Visibility | Delete

Provider	Payment method	Name in shop
<input type="checkbox"/> System standard	Payment in advance	Payment in advance
<input type="checkbox"/> System standard	Invoice	Invoice
<input type="checkbox"/> ZipMoney	CR1	Credit Card

+ [Dropdown menu] [Input field]


Save

PayPal

(Select entry)  
(Select entry)  
Free  
Fixed price  
Exemption limit  
Direct debit  
Direct debit via fax  
Credit card, manual  
Skrill  
Ingenico  
Acceptance  
Credit card using Skrill  
Postfinance  
Website Payments Standard  
POSTPAY  
PayPal Express Checkout  
Website Payments Pro Hosted Solution  
Website Payments Pro Payflow Edition  
WorldPay  
Credit card payment via your bank  
**ZipMoney**

## 2. CONFIGURE AND ACTIVATE ZIPMONEY PAYMENT METHOD

1. On the newly created payment method entry, click **Complete it** link to go to the Settings page.



2. Click the **Settings button**, and fill in the following fields with your zipMoney merchant account details.

**Data for ZipMoney merchant account**

Merchant ID*	<input type="text"/>
Merchant Secret Key*	<input type="text"/>
Merchant Public Key*	<input type="text"/>

- **Merchant ID:** This is your general merchant identifier
- **Merchant Secret Key:** This is your secret API key that will be used for all API communications
- **Merchant Public Key:** This is your public API key that can be used for accessing zipMoney widget library


3. Settings for payment processing.

**Settings for payment processing**

Product type	<input type="text" value="ZipPay"/>	
Transaction type	<input type="text" value="Charge"/>	
Operational mode	<input type="text" value="Test"/>	

- **Product type**
  - **zipPay:** The no interest ever product which offers accounts up to \$1000. If zipPay is selected the payment step remains at your website instead of redirect to ZipMoney website.
  - **zipMoney:** The consumer finance product which can be used for offering promotional interest free terms for larger account limits. If zipMoney is selected the payment step will be navigated to zipMoney website.
- **Transaction type**
  - **Charge:** This option will immediately apply the charge amount to the customer’s account. An approved Charge purchase cannot be cancelled and would require a Refund if it needed to be reversed.
  - **Authorise and Capture:** This option is a two-step process that allows an amount to be pre-authorized against a customer’s account and then settled later by using the Capture endpoint. This approach is recommended when inventory may not be immediately available, or there may be a delayed period until the order or service is fulfilled. An authorised payment can be cancelled prior to Capture by calling the Cancel endpoint.
- **Operational mode:** Set this option to Live if the merchant account is a real transaction account, otherwise select Test.

- Back on the **Settings Menu >> Payment** page – set the zipMoney payment option to visible by checking the box next to the zipMoney logo and clicking the Visibility (eye shaped) icon.



### 3. SETUP ZIPMONEY MARKETING AND DISPLAY FEATURES


#### 3.1 ADD ZIPMONEY WIDGET(S) TO PRODUCT AND CART PAGES

*It is recommended to add the zipMoney marketing widgets. This will allow shoppers to be aware that this payment method is available in your store. It is particularly more attractive for shoppers who already have a zipMoney account, since they know what their available credit limit is and may opt to add more products to their cart.*

- Adding the **Repayment Calculator** widget



- Tick the **Product Page checkbox** to enable Repayment Calculator widget on **each product** page  
[A sample display effect at store front is as below](#)




- Tick the **Cart Page checkbox** to enable Repayment Calculator widget on **basket checkout page**

- Adding Marketing Widgets




- Tick the **Product Page checkbox** to enable Marketing widget on **each product** page

A sample display effect at store front is as below



- Tick the **Cart Page checkbox** to enable Marketing widget on **basket checkout** page
3. Use css class to **adjust widget position**. Please note that the widget position may not be aligned properly on the product or basket checkout pages due to different shop design templates. In such cases please use following css classes to suit your need.
- CSS class **CustomProductRC** for Repayment Calculator display on product page
  - CSS class **.CustomCartRC** for Repayment Calculator display on basket checkout page
  - CSS class **CustomProductMK** for Repayment Calculator display on product page
  - CSS class **CustomCartMK** for Repayment Calculator display on basket checkout page

You will need to manually add these css classes in the **HTML Head area** located at **Settings >> General Settings >> General >> Advanced settings**, e.g.




### 3.2 ADD ZIPMONEY LANDING PAGE TO YOUR WEBSITE MENUS

Create a friendly landing page (static web page) on your eCorner store to allow visitors to activate their shopping accounts. Great for converting browsers to buyers.


1. Go to **Design >> Advanced design**
2. Locate the **Mega menu** and move cursor to the Plus icon then you click **Insert page element**, e.g.



3. On the **Insert new page element** dialog, click **Payment** on the left **Topic area**.
4. Scroll down the available page element of **Payment** until a number of zipMoney page elements show up.



5. Select **zipMoney – Pay Later (Point to landing page)** or select **zipMoney – Buy Now, Pay Later (Point to landing page)** then click **Insert**. The only difference between two elements is the display text.
6. After a landing page element is added, don't forget to **Save** the Advanced design.



### 3.3 ADD ZIPMONEY ICON TO FOOTER SECTION

Ensure that you place the zip payment acceptance icon your footer which links to zipMoney official site.

1. Go to **Design >> Advanced design**
2. Locate the **Footer link** bar and move cursor to the Plus icon then you click **Insert page element**, e.g.



3. On the **Insert new page element** dialog, click **Payment** on the left **Topic area**.
4. Scroll down the available page element of **Payment** until a number of ZipMoney page elements show up.
5. Select **ZipMoney – Icon for zipMoney payment** and click **Insert**.
6. **Save** the Advanced design.

### 3.4 ADD ZIPMONEY LOGO TO YOUR WEBSITE

You can also place the zipMoney logo in anywhere of your website.

1. Go to **Design >> Advanced design**
2. Move cursor to the Plus icon where the zipMoney is to display then click **Insert page element**.
3. On the **Insert new page element** dialog, click **Payment** on the left **Topic area**.
4. Scroll down the available page element of **Payment** until a number of zipMoney page elements show up.
5. Select **zipMoney – Logos for zipMoney payment** and click **Insert**.
6. **Save** the Advanced design.