

Getting More from Your Cloud Shop

Using ePages V6

Going Live with eWAY!

Prepared by:
eCorner Pty Ltd

ABN – 25 107 795 568

Created: January 14

eWAY Payment Setup

Add your eWAY live customer ID to the Merchant Settings Page and change to “Live” then “Save”.

Payment methods + eWAY

General Settings Customer groups

Merchant settings Credit Cards Credit card logos

eWAY Links
 ▶ Create eWAY Account
 ▶ eWAY Business Centre Login

eWAY Customer ID
 12345678

Real-Time payments (Live)

Save

Make sure that you have setup the credit card types that you want and set to “Visible” and “Save”.

Payment methods + eWAY

General Settings Customer groups

Merchant settings Credit Cards Credit card logos

Credit card	Credit Card Verification Number (CVN)	Visible	Sort order
<input type="checkbox"/> Visa	Entry required	<input checked="" type="checkbox"/>	10
<input type="checkbox"/> MasterCard	Entry required	<input checked="" type="checkbox"/>	20
<input type="checkbox"/>	(Select entry)	<input type="checkbox"/>	9999

Save Delete

You can set the credit card logos that will be displayed under the eWAY logo that can be set from the Advanced Design manager.

Payment methods + eWAY

General Settings Customer groups

Merchant settings Credit Cards Credit card logos

Select the accepted credit cards for display in the shop

Visa Debit Visa Electron Visa Credit Mastercard
 Amex Diners UCB Solo
 Laser VisaDelta CB Maestro

Save

Related topics
 ▶ Page design
 Add the navigation element 'Logos for accepted credit cards (eWAY)' to the storefront
 ▶ eWAY Transactions
 Display a list of orders paid via eWAY
 ▶ eWAY Response Codes
 Check the list of error codes your customer might encounter when placing a transaction

In the General tab ensure that the payment method is set to “Visible”. If you cannot change the setting on the page then you can use the batch function.

Payment methods ← eWAY

General Settings Customer groups

ID: eWAY

Type: eWAY

Visible: Yes No

Default: Yes No

Deferred payment available: Yes No

Discount: 0 %

Allow usage for the following billing addresses: All countries of the shop

English

Name in shop: Credit Card by eWAY

Comment: [Edit text]

Save Delete

You can set the payment method to “Visible” using the batch processing function, select the method required and the “Set visible” from the drop down menu and then press “Execute”.

Delivery and payment methods settings

Delivery methods Payment methods Dependencies Delivery options Deferred payment Credit check

<input type="checkbox"/>	Provider	Payment method	Name in shop	Default	Sort order
<input type="checkbox"/>	System standard	Quote	Quote	<input type="radio"/>	10
<input type="checkbox"/>	System standard	Invoice	Invoice	<input type="radio"/>	20
<input type="checkbox"/>	System standard	Cash in Advance	Cash in Advance	<input type="radio"/>	30
<input type="checkbox"/>	PayPal	PayPal Express Checkout <small>Complete it</small>	PayPal Express Checkout	<input type="radio"/>	40
<input checked="" type="checkbox"/>	eWAY	eWAY	Credit Card by eWAY	<input checked="" type="radio"/>	50
<input type="checkbox"/>		(Select entry)			9999

Save

Set visible (Select entry) Add to tray **Set visible** Set not visible Delete

Execute

moneybookers.com

Going live

You can now go live with your online shop. But first, activate your shop’s page cache to speed up surfing for your customers. To do so, either click on the red banner in the uppermost header of your back office or activate the page cache in the "Settings / General settings" menu. Afterwards, you can throw open the doors to your shop in the “Status” submenu.

By the way, it is better to be safe than sorry. Check for yourself that your shop is functioning properly. Make a small purchase in your own online shop and complete every

step of an order. Do not forget to make an actual payment and to verify that the money does indeed end up in your account.